

# *Message Router (MRTR) Operation and Installation Manual*



Capitalware Inc.  
1673 Richmond Street, Suite 524  
London, Ontario N6G2N3  
Canada  
sales@capitalware.biz  
<http://www.capitalware.biz>

# Table of Contents

---

<b>1 INTRODUCTION.....</b>	<b>1</b>
1.1 OVERVIEW.....	1
1.2 CONTEXT DIAGRAM (LOGICAL VIEW).....	1
<b>2 INSTALLING MESSAGE ROUTER.....</b>	<b>2</b>
2.1 WINDOWS INSTALLATION.....	2
2.2 UNIX AND LINUX INSTALLATION.....	2
2.3 IBM I INSTALLATION.....	3
2.4 z/OS INSTALLATION.....	4
<b>3 STARTING MRTR.....</b>	<b>6</b>
3.1 TRIGGERED EXECUTION.....	6
3.2 MANUAL EXECUTION.....	6
3.3 SCHEDULED EXECUTION.....	6
3.4 COMMAND-LINE PARAMETERS.....	6
3.5 z/OS BATCH EXECUTION.....	6
<b>4 INIFILE PARAMETERS.....</b>	<b>7</b>
4.1 LOGGING.....	7
4.2 MQ.....	7
4.3 OTHER.....	8
<b>5 LOG FILE.....</b>	<b>9</b>
5.1 WINDOWS.....	9
5.2 UNIX AND LINUX.....	10
5.3 IBM I.....	11
5.4 z/OS.....	12
<b>6 APPENDIX A – MRTR.INI FILE .....</b>	<b>13</b>
<b>7 APPENDIX A – TECHNICAL SUPPORT .....</b>	<b>15</b>
<b>8 APPENDIX D – SUMMARY OF CHANGES.....</b>	<b>16</b>
<b>9 APPENDIX E – LICENSE AGREEMENT.....</b>	<b>17</b>
<b>10 APPENDIX F – NOTICES.....</b>	<b>21</b>



# 1 Introduction

## 1.1 Overview


**Message Router** (MRTR) is a MQ application that will move a message from a central queue to a specific application queue. The destination queue that the message will be placed into will be based on a keyword in the message. Context information is maintained across the get then message put.

MRTR will look in the message for a Start Keyword and an End Keyword. The value between these two keywords is the Keyword Value (infile Token).

MRTR will search its infile for that particular Keyword Value. The field value associated with the lookup-ed keyword value is the destination queue name.

MRTR performs each MQGET and the subsequent MQPUT under a Unit of Work (UOW), so that message integrity is kept.

## 1.2 Context Diagram (Logical View)



## 2 Installing Message Router

This section describes how to install Capitalware's MRTR.

### 2.1 Windows Installation

To install MRTR on Windows, do the following instructions:

- Run the install program called: **mrtr-setup.exe**
- The installer follows the standard Windows install procedures and provides default values for the user.
- When the install program has completed execution, there will be a newly created folder under *Start -> All Programs* called **MRTR**.
- To run MRTR, select the MRTR icon from within the MRTR folder.

The user may copy or ftp the mrtr.exe and mrtrc.exe files from one Windows server to another Windows server.

### 2.2 Unix and Linux Installation

To install MRTR on Unix or Linux, first unzip the **mrtr.zip** and then select the appropriate TAR file for the target platform. You will find 8 TAR files in the original ZIP file:

- **AIX/mrtr\_aix.tar**
- **HPUX\_IA64 /mrtr\_hpux\_ia64.tar**
- **HPUX\_PA-RISC /mrtr\_hpux.tar**
- **Linux\_x86/mrtr\_linux\_x86.tar**
- **Linux\_POWER/mrtr\_linux\_power.tar**
- **Linux\_zSeries//mrtr\_linux\_zseries.tar**
- **Solaris\_SPARC/mrtr\_solaris.tar**
- **Solaris\_x86/mrtr\_solaris\_x86.tar**

Steps to install the server-side security exit:

1. ftp or copy the selected TAR file to the target platform to the */opt/capitalware/* directory.
2. Un-tar the mrtr\_XXX.tar file into the */opt/capitalware/* sub-directory (XXX is either aix, hpux, solaris or linux)

```
cd /opt/capitalware/  
tar -xvf mrtr_XXX.tar
```

## 2.3 IBM i Installation

To install the MRTR on IBM i, first unzip the **mrtr.zip** and then select the files in the IBM i (iSeries) directory.

- **mrtr.savf** is the IBM i 'Save File' that contains MRTR

Steps to install MRTR:

1. Log onto the target IBM i server and do the following command:

```
CRTSAVF FILE(QGPL/MRTR)
```

2. ftp the IBM i files to the IBM i server as follows:

```
ftp -s:mrtr_iseries.ftp iseries_hostname
```

```
your-IBM i-userid  
your-IBM i-password  
  
binary  
cd QGPL  
put mrtr.savf  
  
quit
```

3. Log onto the target IBM i server and do the following commands:

```
RSTLIB SAVLIB(MRTR) DEV(*SAVF) SAVF(QGPL/MRTR)  
CLRSVF FILE(QGPL/MRTR)  
CHGOBJOWN OBJ(MRTR) OBJTYPE(*LIB) NEWOWN(QMQM)
```

## 2.4 z/OS Installation

To install the MRTR for z/OS, first unzip the **mrtr.zip**. The zip file contains 1 z/OS XMIT prepared dataset.

- **MRTR.LOAD.ZOS** is the XMIT dataset that contains the z/OS load-module.

Steps to install MRTR:

1. ftp the z/OS XMIT prepared datasets to the z/OS LPAR.

**ftp -s:mrtr.ftp z/OS\_hostname**

```
your-z/OS-userid
your-z/OS-password

binary
quote SITE recfm=fb lrecl=80 blksize=3120
put MRTR.LOAD.ZOS
quit
```

If the user receives the following error message then they will need to pre-allocate the z/OS dataset:

```
ftp> put MRTR.LOAD.ZOS
200 Port request OK.
550-SVC99 RETURN CODE=4 S99INFO=0 S99ERROR=38656 HEX=9700 S99ERSN code X'000003F3'.
550 Unable to create data set xxxxx.MRTR.LOAD.ZOS for STOR command.
```

To pre-allocate the XMIT dataset go to option 3.2 of ISPF and allocate the dataset: MRTR.LOAD.ZOS.

Use the following dataset attributes when allocating the dataset:

Space	
Units	BLOCKS
Primary Quantity	40
Secondary Quantity	40
Directory Blocks	0
DCB Parameters	
RECFM	FB
LRECL	80
BLKSIZE	3120
DsnType	Blank

After the user has pre-allocated the dataset, they can redo the ftp commands.

2. Log on to z/OS LPAR and issue the following TSO RECEIVE commands:

**TSO RECEIVE INDATASET(MRTR.LOAD.ZOS)**

After issuing the above commands, the following product dataset will appear:

- **+HLQ+.CPTLWARE.MRTR.LOAD** is the dataset that contains the z/OS load-module.

### 3 Starting MRTR

This section describes the various ways that the MRTR can be started. Currently, MRTR via WebSphere MQ's triggering system, manually or by a scheduling package.

#### 3.1 Triggered Execution

If the local input queue has been setup for triggering (i.e. Trigger First) then when a message arrives on the input queue and the message count goes from 0 to 1 (trigger on first), the queue manager will start MRTR. The Backup component will begin processing each message on the input queue and writing the message's content including MQMD to a file.

#### 3.2 Manual Execution

MRTR can be manually started from a Command Prompt. First change to the MRTR directory (i.e. C:\Capitalware\MRTR ) and then type *mrtr.exe* and then press *Enter*.

#### 3.3 Scheduled Execution

MRTR can be setup to be run under a scheduling package. (For example, Windows 2000 **Scheduled Task** service.) You may prefer to have MRTR executed daily. Therefore, use the scheduling package's tools to setup the necessary parameters for daily execution.

#### 3.4 Command-line parameters

This section describes the required and optional command-line parameters for the MRTR.

```
mrtr.exe [-i Path_FileName_for_inifile]
```

Required Parameter	Description
-i	The full path and filename of the MRTR IniFile.

#### 3.5 z/OS Batch Execution

Here is a sample JCL to run MRTR:

```
//RUN01 EXEC PGM=MRTR, PARM='-i MRTRIN'
//STEPLIB DD DISP=SHR, DSN=+HLQ+.CPTLWARE.MRTR.LOAD
//SYSPRINT DD SYSOUT=*
//SYSOUT DD SYSOUT=*
//MRTRIN DD DISP=SHR, DSN=+HLQ+.CPTLWARE.INIFILE(MRTR)
```

## 4 IniFile Parameters

### 4.1 Logging

- **PerformLogging** specifies what type of logging the user wishes to have. PerformLogging supports 2 values: [Y / N], where Y is Yes and N is No. The default value is N.

PerformLogging =N

- **LogFile** specifies the location of the log file. The default is as follows:

For Windows:

LogFile=C:\Capitalware\MRTR\mrtr.log

For Unix:

LogFile=/opt/capitalware/MRTR/mrtr.log

- **LogMessage** will cause each message to be written to the log file (just the message data). LogMessage supports 2 values: [Y / N]. The default value is N.

LogMessage=N

### 4.2 MQ

- **GetWithConvert** causes MRTR to retrieve messages with or without MQGMO\_CONVERT option. GetWithConvert supports 2 values: [Y / N]. The default value is Y.

GetWithConvert=Y

- **GetBufferSize** specifies the maximum message size to be retrieved from the input queue. GetBufferSize supports values from 1 to 104857600 (100MB). The default value is 65536.

GetBufferSize=65536

- **TimeOut** specifies time-out value for the MQGET function. TimeOut supports values from 1 to 2147483648. The default value is 10 seconds. *Note: To specify 'wait forever' set TimeOut to 0 (zero).*

TimeOut =10

- **QMgrName** specifies the name of the queue manager. There is no default value.

QMgrName = MQA1

- **InputQName** specifies the name of the input queue. There is no default value.

InputQName = MQA1

- **RouterDeadQ** specifies the name of the Message Router's dead letter queue.. There is no default value.

RouterDeadQ = MRTR.DEAD.QUEUE

- **StartKeyword** specifies the beginning marker for the keyword value (token).

StartKeyword = sssss

- **EndKeyword** specifies the ending marker for the keyword value (token).

EndKeyword = eeeee

- **ttttttt** specifies the keyword value (token) that has a destination queue name associated with it. Note: Repeat this item for each keyword value (token) that is required.

tttttt = APP.ABC.QUEUE

### 4.3 Other

- **SequenceNumberFlag** is a z/OS (OS/390) only flag. It states whether or not there are sequence numbers in columns 72 to 80. SequenceNumberFlag supports 2 values; [Y / N]. The default value is N.

SequenceNumberFlag = N

## 5 Log File

To verify that the process flow was successful, you can view the log file for the events that are generated.

### 5.1 Windows

The log file is located at the following (assuming a default install of C:\Capitalware\MRTR )::

**C:\Capitalware\MRTR\mrtr.log**

All log entries will be marked with **INFO**, **WARNING** or **ERROR** in columns 21 to 26.

```

2011/04/08 19:05:33 INFO #00593: *****
2011/04/08 19:05:33 INFO #00597: MRTR is now starting.
2011/04/08 19:05:33 INFO #00605: MRTR version 1.1.0 (Windows)
2011/04/08 19:05:33 INFO #00608: Current Log file is mrtr.log
2011/04/08 19:05:33 INFO #00611: PerformLogging=Y
2011/04/08 19:05:33 INFO #00819: The following are the parameters used for this execution.
2011/04/08 19:05:33 INFO #00829: GetWithConvert : N
2011/04/08 19:05:33 INFO #00847: Queue Manager Name: MQWT1
2011/04/08 19:05:33 INFO #00865: Input Queue Name : INPUT.TEST.QUEUE
2011/04/08 19:05:33 INFO #00884: IA Dead Queue Name: MRTR.DEAD.Q
2011/04/08 19:05:33 INFO #00894: StartKeyword : <TASK>
2011/04/08 19:05:33 INFO #00904: EndKeyword : </TASK>
2011/04/08 19:05:33 INFO #00914: Timeout value : 0
2011/04/08 19:05:33 INFO #00924: Get Buffer Size : 100000
2011/04/08 19:05:33 INFO #01321: MQConn CC=0 RC=0 on connection to MQWT1
2011/04/08 19:05:33 INFO #01502: MQOpen CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:39 INFO #01832: MQGet CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:39 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:39 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:39 INFO #01832: MQGet CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:39 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:39 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:43 INFO #01832: MQGet CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:43 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:43 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:43 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:43 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:44 INFO #01832: MQGet CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:44 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:44 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:44 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:44 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:47 INFO #01832: MQGet CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:47 INFO #01838: Quit message received - time to go.
2011/04/08 19:05:47 INFO #01591: MQClose CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:47 INFO #01403: MQDisc CC=0 RC=0 on disconnecting from MQWT1
2011/04/08 19:05:47 INFO #00973: Statistics of this executions:
2011/04/08 19:05:47 INFO #00983: Messages Read : 5
2011/04/08 19:05:47 INFO #00993: Messages Written : 4
2011/04/08 19:05:47 INFO #00999: MRTR is now stopping.

```

## 5.2 Unix and Linux

The log file is located at the following (assuming a default install of /opt/capitalware/MRTR/ ):

**/opt/capitalware/MRTR/mrtr.log**

All log entries will be marked with **INFO**, **WARNING** or **ERROR** in columns 21 to 26.

```

2011/04/08 19:05:33 INFO #00593: *****
2011/04/08 19:05:33 INFO #00597: MRTR is now starting.
2011/04/08 19:05:33 INFO #00605: MRTR version 1.1.0 (AIX)
2011/04/08 19:05:33 INFO #00608: Current Log file is mrtr.log
2011/04/08 19:05:33 INFO #00611: PerformLogging=Y
2011/04/08 19:05:33 INFO #00819: The following are the parameters used for this execution.
2011/04/08 19:05:33 INFO #00829:   GetwithConvert      : N
2011/04/08 19:05:33 INFO #00847:   Queue Manager Name: MQWT1
2011/04/08 19:05:33 INFO #00865:   Input Queue Name  : INPUT.TEST.QUEUE
2011/04/08 19:05:33 INFO #00884:   IA Dead Queue Name: MRTR.DEAD.Q
2011/04/08 19:05:33 INFO #00894:   StartKeyword      : <TASK>
2011/04/08 19:05:33 INFO #00904:   EndKeyword        : </TASK>
2011/04/08 19:05:33 INFO #00914:   Timeout value     : 0
2011/04/08 19:05:33 INFO #00924:   Get Buffer Size   : 100000
2011/04/08 19:05:33 INFO #01321: MQConn CC=0 RC=0 on connection to MQWT1
2011/04/08 19:05:33 INFO #01502: MQOpen CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:39 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:39 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:39 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:39 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:39 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:39 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:43 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:43 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:43 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:43 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:43 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:44 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:44 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:44 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:44 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:44 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:47 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:47 INFO #01838: Quit message received - time to go.
2011/04/08 19:05:47 INFO #01591: MQClose CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:47 INFO #01403: MQDisc  CC=0 RC=0 on disconnecting from MQWT1
2011/04/08 19:05:47 INFO #00973: Statistics of this executions:
2011/04/08 19:05:47 INFO #00983:   Messages Read    : 5
2011/04/08 19:05:47 INFO #00993:   Messages Written : 4
2011/04/08 19:05:47 INFO #00999: MRTR is now stopping.

```

### 5.3 IBM i

The log file is located at the following (assuming a default install of QIBM/UserData/capitalware/MRTR/):

**QIBM/UserData/capitalware/MRTR/mrtr.log**

All log entries will be marked with **INFO**, **WARNING** or **ERROR** in columns 21 to 26.

```

2011/04/08 19:05:33 INFO #00593: *****
2011/04/08 19:05:33 INFO #00597: MRTR is now starting.
2011/04/08 19:05:33 INFO #00605: MRTR version 1.1.0 (iSeries)
2011/04/08 19:05:33 INFO #00608: Current Log file is mrtr.log
2011/04/08 19:05:33 INFO #00611: PerformLogging=Y
2011/04/08 19:05:33 INFO #00819: The following are the parameters used for this execution.
2011/04/08 19:05:33 INFO #00829:   GetWithConvert      : N
2011/04/08 19:05:33 INFO #00847:   Queue Manager Name: MQWT1
2011/04/08 19:05:33 INFO #00865:   Input Queue Name  : INPUT.TEST.QUEUE
2011/04/08 19:05:33 INFO #00884:   IA Dead Queue Name: MRTR.DEAD.Q
2011/04/08 19:05:33 INFO #00894:   StartKeyword      : <TASK>
2011/04/08 19:05:33 INFO #00904:   EndKeyword        : </TASK>
2011/04/08 19:05:33 INFO #00914:   Timeout value     : 0
2011/04/08 19:05:33 INFO #00924:   Get Buffer Size   : 100000
2011/04/08 19:05:33 INFO #01321: MQConn CC=0 RC=0 on connection to MQWT1
2011/04/08 19:05:33 INFO #01502: MQOpen CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:39 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:39 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:39 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:39 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:39 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:39 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:43 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:43 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:43 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:43 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:43 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:44 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:44 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:44 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:44 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:44 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:47 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:47 INFO #01838: Quit message received - time to go.
2011/04/08 19:05:47 INFO #01591: MQClose CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:47 INFO #01403: MQDisc CC=0 RC=0 on disconnecting from MQWT1
2011/04/08 19:05:47 INFO #00973: Statistics of this executions:
2011/04/08 19:05:47 INFO #00983:   Messages Read    : 5
2011/04/08 19:05:47 INFO #00993:   Messages Written : 4
2011/04/08 19:05:47 INFO #00999: MRTR is now stopping.

```

## 5.4 z/OS

The log file is located at the following (assuming a default install of SYSPRINT):

All log entries will be marked with **INFO**, **WARNING** or **ERROR** in columns 21 to 26.

```

2011/04/08 19:05:33 INFO #00593: *****
2011/04/08 19:05:33 INFO #00597: MRTR is now starting.
2011/04/08 19:05:33 INFO #00605: MRTR version 1.1.0 (zOS)
2011/04/08 19:05:33 INFO #00608: Current Log file is SYSPRINT
2011/04/08 19:05:33 INFO #00611: PerformLogging=Y
2011/04/08 19:05:33 INFO #00819: The following are the parameters used for this execution.
2011/04/08 19:05:33 INFO #00829:   GetWithConvert      : N
2011/04/08 19:05:33 INFO #00847:   Queue Manager Name: MQWT1
2011/04/08 19:05:33 INFO #00865:   Input Queue Name  : INPUT.TEST.QUEUE
2011/04/08 19:05:33 INFO #00884:   IA Dead Queue Name: MRTR.DEAD.Q
2011/04/08 19:05:33 INFO #00894:   StartKeyword      : <TASK>
2011/04/08 19:05:33 INFO #00904:   EndKeyword        : </TASK>
2011/04/08 19:05:33 INFO #00914:   TimeOut value     : 0
2011/04/08 19:05:33 INFO #00924:   Get Buffer Size    : 100000
2011/04/08 19:05:33 INFO #01321: MQConn CC=0 RC=0 on connection to MQWT1
2011/04/08 19:05:33 INFO #01502: MQOpen CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:39 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:39 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:39 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:39 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:39 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:39 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:39 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:43 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:43 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:43 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:43 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:43 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:44 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:44 INFO #01969: Found NoticeSent between <TASK> and </TASK>
2011/04/08 19:05:44 INFO #02001: Output Queue will be OUTPUT.TEST.QUEUE1
2011/04/08 19:05:44 INFO #02116: MQPut1 CC=0 RC=0 for OUTPUT.TEST.QUEUE1
2011/04/08 19:05:44 INFO #02199: MQCmit CC=0 RC=0
2011/04/08 19:05:47 INFO #01832: MQGet  CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:47 INFO #01838: Quit message received - time to go.
2011/04/08 19:05:47 INFO #01591: MQClose CC=0 RC=0 for INPUT.TEST.QUEUE
2011/04/08 19:05:47 INFO #01403: MQDisc CC=0 RC=0 on disconnecting from MQWT1
2011/04/08 19:05:47 INFO #00973: Statistics of this executions:
2011/04/08 19:05:47 INFO #00983:   Messages Read      : 5
2011/04/08 19:05:47 INFO #00993:   Messages Written   : 4
2011/04/08 19:05:47 INFO #00999: MRTR is now stopping.

```

## 6 Appendix A – mrtr.ini file

The table below is the supplied mrtr.ini file. The IniFile supports the following keywords and their values:

```
InputQName = INPUT.TEST.QUEUE
RouterDeadQ = MQTR.DEAD.Q
StartKeyword= <TASK>
EndKeyword = </TASK>
NoticeSent = OUTPUT.TEST.QUEUE1
```

**Note: Keywords are case sensitive.**

Initialization keyword definitions:

- **PerformLogging** specifies what type of logging the user wishes to have. PerformLogging supports 2 values: [Y / N], where Y is Yes and N is No. The default value is N.

PerformLogging =N

- **LogFile** specifies the location of the log file. The default is as follows:

For Windows:

LogFile=C:\Capitalware\MRTR\mrtr.log

For Unix:

LogFile=/opt/capitalware/MRTR/mrtr.log

- **LogMessage** will cause each message to be written to the log file (just the message data). LogMessage supports 2 values: [Y / N]. The default value is N.

LogMessage=N

- **GetWithConvert** causes MRTR to retrieve messages with or without MQGMO\_CONVERT option. GetWithConvert supports 2 values: [Y / N]. The default value is Y.

GetWithConvert=Y

- **GetBufferSize** specifies the maximum message size to be retrieved from the input queue. GetBufferSize supports values from 1 to 104857600 (100MB). The default value is 65536.

GetBufferSize=65536

- **TimeOut** specifies time-out value for the MQGET function. TimeOut supports values from 1 to 2147483648. The default value is 10 seconds. *Note: To specify 'wait forever' set TimeOut to 0 (zero).*

TimeOut = 10

- **QMgrName** specifies the name of the queue manager. There is no default value.

QMgrName = MQA1

- **InputQName** specifies the name of the input queue. There is no default value.

InputQName = MQA1

- **RouterDeadQ** specifies the name of the Message Router's dead letter queue.. There is no default value.

RouterDeadQ = MRTR.DEAD.QUEUE

- **StartKeyword** specifies the beginning marker for the keyword value (token).

StartKeyword = ssssss

- **EndKeyword** specifies the ending marker for the keyword value (token).

EndKeyword = eeeee

- **ttttttt** specifies the keyword value (token) that has a destination queue name associated with it. Note: Repeat this item for each keyword value (token) that is required.

tttttt = APP.ABC.QUEUE

- **SequenceNumberFlag** is a z/OS (OS/390) only flag. It states whether or not there are sequence numbers in columns 72 to 80. SequenceNumberFlag supports 2 values; [Y / N]. The default value is N.

SequenceNumberFlag = N

## **7 Appendix A – Technical Support**

The support for MRTR can be found at the following location (requires a support contract):

**Online Help Desk Ticketing System at**  
[www.capitalware.biz/phpst/](http://www.capitalware.biz/phpst/)

**By email at:**  
[support@capitalware.biz](mailto:support@capitalware.biz)

**By regular mail at:**

Capitalware Inc.  
Attn: MRTR Support  
1673 Richmond Street, Suite 524  
London, Ontario N6G2N3  
Canada

## 8 Appendix D – Summary of Changes

- MRTR v1.1.0
  - Added GetWithConvert keyword
  - Enhanced commit/backout processing
  - Created binaries/executables for all major platforms
  
- MRTR v1.0.0
  - Initial release.

## 9 Appendix E – License Agreement

Apache License  
Version 2.0, January 2004  
<http://www.apache.org/licenses/>

### TERMS AND CONDITIONS FOR USE, REPRODUCTION, AND DISTRIBUTION

#### 1. Definitions.

"License" shall mean the terms and conditions for use, reproduction, and distribution as defined by Sections 1 through 9 of this document.

"Licensor" shall mean the copyright owner or entity authorized by the copyright owner that is granting the License.

"Legal Entity" shall mean the union of the acting entity and all other entities that control, are controlled by, or are under common control with that entity. For the purposes of this definition, "control" means (i) the power, direct or indirect, to cause the direction or management of such entity, whether by contract or otherwise, or (ii) ownership of fifty percent (50%) or more of the outstanding shares, or (iii) beneficial ownership of such entity.

"You" (or "Your") shall mean an individual or Legal Entity exercising permissions granted by this License.

"Source" form shall mean the preferred form for making modifications, including but not limited to software source code, documentation source, and configuration files.

"Object" form shall mean any form resulting from mechanical transformation or translation of a Source form, including but not limited to compiled object code, generated documentation, and conversions to other media types.

"Work" shall mean the work of authorship, whether in Source or Object form, made available under the License, as indicated by a copyright notice that is included in or attached to the work (an example is provided in the Appendix below).

"Derivative Works" shall mean any work, whether in Source or Object form, that is based on (or derived from) the Work and for which the editorial revisions, annotations, elaborations, or other modifications represent, as a whole, an original work of authorship. For the purposes of this License, Derivative Works shall not include works that remain separable from, or merely link (or bind by name) to the interfaces of, the Work and Derivative Works thereof.

"Contribution" shall mean any work of authorship, including the original version of the Work and any modifications or additions to that Work or Derivative Works thereof, that is intentionally submitted to Licensor for inclusion in the Work by the copyright owner or by an individual or Legal Entity authorized to submit on behalf of the copyright owner. For the purposes of this

definition, "submitted" means any form of electronic, verbal, or written communication sent to the Licensor or its representatives, including but not limited to communication on electronic mailing lists, source code control systems, and issue tracking systems that are managed by, or on behalf of, the Licensor for the purpose of discussing and improving the Work, but excluding communication that is conspicuously marked or otherwise designated in writing by the copyright owner as "Not a Contribution."

"Contributor" shall mean Licensor and any individual or Legal Entity on behalf of whom a Contribution has been received by Licensor and subsequently incorporated within the Work.

2. **Grant of Copyright License.** Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable copyright license to reproduce, prepare Derivative Works of, publicly display, publicly perform, sublicense, and distribute the Work and such Derivative Works in Source or Object form.

3. **Grant of Patent License.** Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable (except as stated in this section) patent license to make, have made, use, offer to sell, sell, import, and otherwise transfer the Work, where such license applies only to those patent claims licensable by such Contributor that are necessarily infringed by their Contribution(s) alone or by combination of their Contribution(s) with the Work to which such Contribution(s) was submitted. If You institute patent litigation against any entity (including a cross-claim or counterclaim in a lawsuit) alleging that the Work or a Contribution incorporated within the Work constitutes direct or contributory patent infringement, then any patent licenses granted to You under this License for that Work shall terminate as of the date such litigation is filed.

4. **Redistribution.** You may reproduce and distribute copies of the Work or Derivative Works thereof in any medium, with or without modifications, and in Source or Object form, provided that You meet the following conditions:

(a) You must give any other recipients of the Work or Derivative Works a copy of this License; and

(b) You must cause any modified files to carry prominent notices stating that You changed the files; and

(c) You must retain, in the Source form of any Derivative Works that You distribute, all copyright, patent, trademark, and attribution notices from the Source form of the Work, excluding those notices that do not pertain to any part of the Derivative Works; and

(d) If the Work includes a "NOTICE" text file as part of its distribution, then any Derivative Works that You distribute must include a readable copy of the attribution notices contained within such NOTICE file, excluding those notices that do not pertain to any part of the Derivative Works, in at least one of the following places: within a NOTICE text file distributed as part of the Derivative Works; within the Source form or documentation, if provided along with the Derivative Works; or, within a display generated by the Derivative Works, if and wherever such third-party notices normally appear. The contents of the NOTICE file are for

informational purposes only and do not modify the License. You may add Your own attribution notices within Derivative Works that You distribute, alongside or as an addendum to the NOTICE text from the Work, provided that such additional attribution notices cannot be construed as modifying the License.

You may add Your own copyright statement to Your modifications and may provide additional or different license terms and conditions for use, reproduction, or distribution of Your modifications, or for any such Derivative Works as a whole, provided Your use, reproduction, and distribution of the Work otherwise complies with the conditions stated in this License.

5. Submission of Contributions. Unless You explicitly state otherwise, any Contribution intentionally submitted for inclusion in the Work by You to the Licensor shall be under the terms and conditions of this License, without any additional terms or conditions. Notwithstanding the above, nothing herein shall supersede or modify the terms of any separate license agreement you may have executed with Licensor regarding such Contributions.

6. Trademarks. This License does not grant permission to use the trade names, trademarks, service marks, or product names of the Licensor, except as required for reasonable and customary use in describing the origin of the Work and reproducing the content of the NOTICE file.

7. Disclaimer of Warranty. Unless required by applicable law or agreed to in writing, Licensor provides the Work (and each Contributor provides its Contributions) on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied, including, without limitation, any warranties or conditions of TITLE, NON-INFRINGEMENT, MERCHANTABILITY, or FITNESS FOR A PARTICULAR PURPOSE. You are solely responsible for determining the appropriateness of using or redistributing the Work and assume any risks associated with Your exercise of permissions under this License.

8. Limitation of Liability. In no event and under no legal theory, whether in tort (including negligence), contract, or otherwise, unless required by applicable law (such as deliberate and grossly negligent acts) or agreed to in writing, shall any Contributor be liable to You for damages, including any direct, indirect, special, incidental, or consequential damages of any character arising as a result of this License or out of the use or inability to use the Work (including but not limited to damages for loss of goodwill, work stoppage, computer failure or malfunction, or any and all other commercial damages or losses), even if such Contributor has been advised of the possibility of such damages.

9. Accepting Warranty or Additional Liability. While redistributing the Work or Derivative Works thereof, You may choose to offer, and charge a fee for, acceptance of support, warranty, indemnity, or other liability obligations and/or rights consistent with this License. However, in accepting such obligations, You may act only on Your own behalf and on Your sole responsibility, not on behalf of any other Contributor, and only if You agree to indemnify, defend, and hold each Contributor harmless for any liability incurred by, or claims asserted against, such Contributor by reason of your accepting any such warranty or additional liability.

END OF TERMS AND CONDITIONS



Copyright 2009 Capitalware Inc.

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

## 10 Appendix F – Notices

### **Trademarks:**

AIX, IBM, MQSeries, OS/2 Warp, OS/400, iSeries, MVS, OS/390, WebSphere, WebSphere MQ and z/OS are trademarks of International Business Machines Corporation.

HP-UX is a trademark of Hewlett-Packard Company.

Intel is a registered trademark of Intel Corporation.

Java, J2SE, J2EE, Sun and Solaris are trademarks of Sun Microsystems Inc.

Linux is a trademark of Linus Torvalds.

Mac OS X is a trademark of Apple Computer Inc.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation.

UNIX is a registered trademark of the Open Group.

WebLogic is a trademark of BEA Systems Inc.